

# Iodine-131 Carcinoma Tx Inpatient Record

## FINAL ROOM SURVEY

Patient Name: \_\_\_\_\_ Room No.: \_\_\_\_\_  
 Date: \_\_\_\_/\_\_\_\_/\_\_\_\_ Cleanup Start Time: \_\_\_\_\_ Cleanup Finish Time: \_\_\_\_\_

### FOLLOW IODINE - 131 THERAPY FINAL SURVEY PROCEDURE

1. With the patient removed from the room, record initial survey data from an EWGM meter.
2. Wipe smears for initial removable contamination are to be placed in appropriately marked test tubes.
3. Decontaminate with EDTA solution and wash rags the surfaces of the room fixtures, i.e. bed, bedside table, phone, call button, sink, toilet, etc.
4. Repeat steps 1 & 2 as per final survey procedure and record data below.
5. **Any area which is >200 dpm will require decontamination ALARA.**

<u>LOCATION / ITEM</u>	<u>INITIAL</u>		<u>POST-DECONTAMINATION</u>	
	<u>mR/hr</u>	<u>dpm</u>	<u>mR/hr</u>	<u>dpm</u>
<u>BACKGROUND</u>	_____	_____	<u>N/A</u>	<u>N/A</u>
<u>PHONE</u>	_____	_____	_____	_____
<u>CALL BUTTON</u>	_____	_____	_____	_____
<u>BED</u>	_____	_____	_____	_____
<u>BEDSIDE TABLE</u>	_____	_____	_____	_____
<u>SINK</u>	_____	_____	_____	_____
<u>SINK HANDLES</u>	_____	_____	_____	_____
<u>TOILET BOWL RIM</u>	_____	_____	_____	_____
<u>TOILET SEAT</u>	_____	_____	_____	_____
<u>FLOOR</u>	_____	_____	_____	_____
<u>RAD WASTE</u>	_____	_____	_____	_____
<u>RAD LINEN</u>	_____	_____	_____	_____

\_\_\_\_\_ Room was decontaminated to background levels ALARA and released for normal use.  
 \_\_\_\_\_ Room is restricted for decay until: \_\_\_\_\_

Surveyor: \_\_\_\_\_ RSO: \_\_\_\_\_